

Uninstalling the Bridge

To make sure the BRIDGE will be uninstalled correctly, read the description carefully, as there are significant differences between

- wanting to remove a BRIDGE instance from a multiple BRIDGE installation and
- wanting to remove a Single BRIDGE installation.

You need administration rights to perform the steps described below.

Stopping the Services and the BRIDGE

1. Stop all running services on the BRIDGE.
2. If a deployed service was using a proxy, stop the Proxy Server in the BRIDGE.
3. Stop the Windows service/Linux daemon of the BRIDGE (**E2E Console**) on the system.

On Linux systems, you need to login as root user and execute the following command:

```
/etc/init.d/e2e_console stop <DNS name>
```

Manual Removal of a Single BRIDGE Installation

Follow the steps below to remove a Single BRIDGE Installation or the last server instance of a Multiple BRIDGE Installation.

1. Removing the Directories

- Remove the installation directory of the BRIDGE (default location: **C:\E2E_BRIDGE_PROG** resp. **/opt/e2e_bridge_prog**).
- Optionally, remove the data directory of the BRIDGE containing the composite services (default location: **C:\E2E_BRIDGE_DATA** resp. **/opt/e2e_bridge_data**).
If you decide to **not** remove the data directory, you need to remove the following files from this directory:
 - data.properties
 - domain\nodes.xml

If these files are not removed, and you try to re-install the BRIDGE, the installer will use the old installation parameters and perform an update installation.

2. Removing the Registry Entries (Windows only)

- With a installation in workstation mode, use a command shell to remove the following registry entries:

```
sc.exe delete E2EConsole-localhost
sc.exe delete E2EProxies-localhost
```

- With a installation in server mode, use a command shell to remove the following registry entries:

```
sc.exe delete E2EConsole-<fully qualified domain name>
sc.exe delete E2EProxies-<fully qualified domain name>
```

For example:

```
sc.exe delete E2EConsole-bridge.scheer-acme.com
sc.exe delete E2EProxies-bridge.scheer-acme.com
```

Look at the Windows Services dialog for your fully qualified domain name.

On this Page:


- [Stopping the Services and the BRIDGE](#)
- [Manual Removal of a Single BRIDGE Installation](#)
 - [Removing the Directories](#)
 - [Removing the Registry Entries \(Windows only\)](#)
 - [Removing the Files \(Linux only\)](#)
- [Removing Bridges from a Multiple BRIDGE Installation](#)
 - [Editing the Files \(Linux only\)](#)
 - [Removing the Directories](#)
 - [Removing the Registry Entries \(Windows only\)](#)


Related Documentation:

- [Starting and Stopping xUML Services](#)
- [Starting and Stopping the Proxy Service](#)

3. Removing the Files (Linux only)

- Remove the BRIDGE startup file .
- Remove the following links to the startup file.
These links are used for the start of the BRIDGE service on system startup.

 If you did not check the option **Start E2E Bridge service on system startup** during the installation of the BRIDGE, these links were not created by the installer.

 In each folder **rc2.d** and **rc3.d**, there are two files starting with letter **K** or **S**, **followed by a number and e2e_console**. However, the number (here **99**) may be different as they were generated by the operation system. Make sure to remove all four files.

```
/etc/rc0.d/K99e2e_console  
/etc/rc1.d/K99e2e_console  
/etc/rc2.d/K99e2e_console  
/etc/rc3.d/S99e2e_console  
/etc/rcS.d/K99e2e_console
```

- Remove the file **/root/.e2econsole**, if existent. This file comes from older BRIDGE versions.

Removing Bridges from a Multiple BRIDGE Installation

Follow the steps below to remove an additional BRIDGE from a Multiple BRIDGE installation.

If you are removing the **last** BRIDGE instance of a Multiple BRIDGE Installation, refer to section [Manual Removal of a Single BRIDGE Installation](#).

1. Editing the Files (Linux only)

Edit the Console startup file **/etc/init.d/e2e_console** as follows.

Locate the lines that define **CONSOLE_HOSTNAMES** and **CONSOLE_HOMES**, for instance:

```
CONSOLE_HOSTNAMES="bridge.scheer-acme.com bridge2.scheer-acme.com"  
CONSOLE_HOMES="/opt/e2e_bridge_prog /opt/e2e_bridge_prog2"
```

Remove the entries for the node you want to remove, for instance **bridge2.scheer-acme.com**, which is installed in folder **/opt/e2e_bridge_prog2**.
After editing the file, both lines would look like this:

```
CONSOLE_HOSTNAMES="bridge.scheer-acme.com"  
CONSOLE_HOMES="/opt/e2e_bridge_prog"
```

2. Removing the Directories

- Remove the installation directory of the BRIDGE (default location: **C:\<program directory of the bridge>**).
- Optionally, remove the data directory of the BRIDGE containing the composite services (default location: **C:\<data directory of the bridge>**).

If you decide to **not** remove the data directory, you need to remove the following files from this directory:

- data.properties
- domain\nodes.xml

If these files are not removed, and you try to re-install the BRIDGE, the installer will use the old installation parameters and perform an update installation.

3. Removing the Registry Entries (Windows only)

- Use a command shell to remove the following registry entries:

```
sc.exe delete E2EConsole-<fully qualified domain name>  
sc.exe delete E2EProxies-<fully qualified domain name>
```

For example:

```
sc.exe delete E2EConsole-bridge2.scheer-acme.com  
sc.exe delete E2EProxies-bridge2.scheer-acme.com
```