

Deployment of xUML Services

xUML services normally are deployed via the Builder for MagicDraw. In the component diagram of a UML model in MagicDraw™, you define the control port number and the Bridge node instance, to which the composite of the service will be deployed. Then, you can compile and deploy the service to the defined node instance with the [xUML Model Compiler](#).

You can also directly deploy the repository of a compiled composite to a node instance via the Bridge.

How to manage service repositories for different environments like Development, Test, or Production is explained in detail in [Configuration Management](#).

The control port is defined in the component diagram and is used for the communication between the console and the server component. If a compiled composite is deployed to a server, the Bridge will check whether the xUML service is already existing on the Bridge. If you have chosen the option to overwrite the xUML service, and existing (old) xUML service will be overwritten. If the control port has changed, the new control port will be used. The old control port will be released. If you have not chosen to overwrite the composite, the Bridge will report an error, because composite names of a node instance must be unique.

It is possible to deploy two different xUML services with the same control port. However, if the control port is already used by one composite, the other composite cannot be started unless the first composite is stopped.

Bridge 7.0.0 Please note that repositories that have been compiled with a Bridge 7 compiler cannot be deployed to Bridges older than 6.0.55.2.

On this Page:

- [Deploying an xUML Service via the Bridge](#)

Related Pages:

- [Deployment of Node.js Services](#)
- [Deployment of Java Services](#)
- [xUML Service Details](#)
- [Frontend Components](#)
- [The xUML Model Compiler](#)
- [Configuration Management](#)

Deploying an xUML Service via the Bridge

Only users who are member of a group, to which the role **ADMIN** or **MODELER** has been assigned, are allowed to deploy xUML services. Users, who have only **MODELER** access rights, may only replace an xUML service, if they themselves or a member of the same group deployed it.

If a composite has already been compiled in the Builder, you can select and deploy the generated REP file that contains the repository files and the WSDL file.

Select the navigation item **Deployment** in the **Domain** section of the navigation on the left to deploy a new xUML service or overwrite an existing one.



Locate and select the REP file by clicking **Browse...**

The REP file is located in the repository directory as defined in the Builder project settings. Start the Builder, open the Builder project settings, and switch to the tab **General** to look up this directory.

Click **Upload ...** to proceed with uploading the repository and setting the deployment options.

Deployment

xUML RepositoryHelloWorldExample.rep

Service NameHelloWorldExample

Deploy Settings and Preferences from Repository☐

Startup Service☐

	New	Deployed
Service Version	7.0.0	-
Compiler Version	7.1.0-c33a278	-
Build Time	2018-10-05 09:24:42	-

DeployCancel

Deployment

xUML RepositoryHelloWorldExample.rep

Service NameHelloWorldExample

Deploy Settings and Preferences from Repository☐

Startup Service☐

	New	Deployed
Service Version	7.1.0	7.0.0
Compiler Version	7.1.0-29a7683	7.1.0-c33a278
Build Time	2018-10-09 11:00:41	2018-10-05 09:24:42

OverwriteCancel

Two tables show an overview on the details of the service to be deployed:

Name	Description
xUML Repository	File name of the service repository.
Service Name	Name of the service component.
Service Version	Service version as specified on the service component (see Frontend Components).
Compiler Version	Version of the compiler the service has been compiled with.
Build Time	Build time of the service repository.

If the service has been deployed to this node instance before, you can compare the details of the new and the existing service here.

Furthermore, you can set the following deployment options:

Option	Description
Deploy Settings and Preferences from Repository	This option is enabled only, if the repository to be uploaded comes from a service export and contains exported settings and preferences. Check this option, if you want to also deploy the exported settings and preference. If you are overwriting an existing xUML service, settings and preferences will be added from the repository – all locally changed settings and preferences will get overwritten.
Startup Service	To run, the xUML service has to be started. Select this option, if you want the xUML service to be started automatically right after its deployment.

After you have set all options, deploy the composite by clicking **Deploy**. If the service already exists, the button will read **Overwrite**.

If you have deployed a new xUML service, it will be displayed in the navigation, below the node instance, to which it has been deployed. The target node instance, to which the xUML service will be deployed, is specified in the component diagram of the UML model in the Builder and is stored in the deployment descriptor of the repository files.

Additionally, a backup copy of the deployed service will be made to <your Bridge data directory>/backup. This backup includes the service settings as present on the Bridge after deployment - depending on what you specified for option **Deploy Settings and Preferences from Repository**.