
















Adapting the Configuration of Containerized xUML Services Kubernetes

 This option is only available for type **xuml-service** (= containerized xUML services).

The administration application allows you to change the configuration of a containerized xUML service.

| Name ↑ | Type | Quick Actions |
|--|--------------|---|
|  acme-idea-management | xuml-service |       |
|  ticketssystem | xuml-service |       |

The administration application allows you to change the configuration of a Kubernetes workload.

You have two options to open the configuration:

- Use option **Edit configuration** from the quick actions bar in the services' list.

On this Page:

- [Changing xUML Service Settings](#)
 - [Assigning a Global Variable](#)
 - [Filtering the Settings' List](#)
- [xUML Service Settings](#)
 - [Global Settings](#)
 - [Add-on Settings](#)
 - [SQL Adapter Connection Settings](#)
 - [SQL Adapter Authorization Settings](#)
 - [Other Add-on Settings](#)
- [Expert Mode](#)

Related Pages:

- [Working With the Administration](#)
 - [Working With the Deployment Wizard](#)
- [Controlling Containerized xUML Services](#)
 - [Changing the Log Level of a Containerized xUML Service](#)
 - [Managing Global Variables for Containerized xUML Services](#)
 - [Persistent States of Containerized xUML Services](#)
 - [Showing Logs of a Containerized xUML Service](#)
- [Controlling Kubernetes Workloads](#)

Details of ticketsystem

← **running** ▶ ■ ↻

Information

Kubernetes


Details

Documentation

Logs

History Log

Persistent State


Configuration 

- Open the details page of the service and scroll down to section **Configuration**.

Changing xUML Service Settings

Change Configuration

Filter Expert Mode Invalid 3 Edited 1 / 73

| Category | Section | Key | Name | Current Value | Default Value |
|-----------------|------------------------------|--|--|-------------------------------------|---------------|
| Global Settings | Settings / Deployment Macros | ~AuthenticatorEnabled | G_AUTHENTICATORENABLED | <input checked="" type="checkbox"/> | true |
| Global Settings | Settings / Deployment Macros | Simple_Form_example_holdTime | G_SIMPLE_FORM_EXAMPLE_HOLDTIME | <input type="text" value="PT60S"/> | PT60S |
| Global Settings | Settings / Deployment Macros | Simple_Form_example_autoRetry | G_SIMPLE_FORM_EXAMPLE_AUTORETRY | <input type="checkbox"/> | false |
| Add-Ons | SAP Global | DefaultConnectionPoolSize | AO_SETTINGS_DEFAULT_CONNECTIONPOOLSIZE | <input type="text" value="101"/> | 10 |
| Add-Ons | SOAP HTTP Service Request |  BPMN_RESTService: Rest URI | addOn_BPMN_RESTService: Rest URI | <input type="text" value="/rest"/> | /rest |

Items 5 1 - 5 / 73 |< >|

Save Cancel

In the **Configuration** section you can directly modify xUML service settings. When you save your changes, the container will be re-created and restarted. Changes are possible after the first deployment of the containerized service.

Change Configuration


Filter Expert Mode Invalid 3 Edited 1 / 73

| Category | Section | Key | Name | Current Value | Default Value |
|-----------------|------------------------------|--|---------------------------------------|---------------|---------------|
| Global Settings | Settings / Deployment Macros | :AuthenticatorEnabled: | G_AUTHENTICATORENABLED | String* true | true |
| Global Settings | Settings / Deployment Macros | Simple_form_example:holdTime: | G_SIMPLE_FORM_EXAMPLE_HOLDTIME | String* PT60S | PT60S |
| Global Settings | Settings / Deployment Macros | Simple_form_example:autoRetry: | G_SIMPLE_FORM_EXAMPLE_AUTORETRY | String* false | false |
| Add-Ons | SAP Global | DefaultConnectionPoolSize: | AD_SETTINGS_DEFAULTCONNECTIONPOOLSIZE | String* 101 | 10 |
| Add-Ons | SOAP HTTP Service Request | Invalid BPMN_RESTService: Rest URL: | addOnBPMN_RESTService_RestURL | String /rest | /rest |

Items 5 1-5 / 73 |< < > >|

Save Cancel

Service settings can be erroneous if a setting name contains special characters or whitespaces. Invalid

service settings are marked . Their number is also displayed on top right of the list.






If a service setting is erroneous, you cannot change its current value.

In case that your service contains erroneous settings, you can do the following:

- If it is a setting in a Designer service ("custom value"): Open the service in the [Designer](#), correct the settings' name and redeploy the service.
- If it is a setting in a platform service, please contact our [support team](#).

Change Configuration

Filter Expert Mode Invalid 3 Edited 0 / 73




| Category | Section | Key | Current Value | Default Value |
|-----------------|------------------------------|--|---|---------------|
| Global Settings | Settings / Deployment Macros | :AuthenticatorEnabled: | String* true  | true |
| Global Settings | Settings / Deployment Macros | Simple_form_example:holdTime: | String* PT60S  | PT60S |
| Global Settings | Settings / Deployment Macros | Simple_form_example:autoRetry: | String* false  | false |
| Add-Ons | SAP Global | DefaultConnectionPoolSize: | String* 101  | 10 |
| Add-Ons | SOAP HTTP Service Request | Invalid BPMN_RESTService: Rest URL: | String /rest  | /rest |

Items 5 1-5 / 73 |< < > >|

Save Cancel



You can change the **Current Value** of a service setting: Just overwrite the displayed value.

The field offers you three additional options:

| Icon | Option | Description |
|--|-------------------------------|---|
|  | Assign Global Variable | Use this option to apply a global variable, see Assigning a Global Variable for details. |
|  | Reset to Default | Use this option to reset the setting to its default. For your information, the Default Value is displayed next to the current value. |
|  | Clear Value | Use this option to remove the content of the Current Value field. |

Change Configuration

Filter Expert Mode Invalid 3 Edited 2 / 73

| Category | Section | Key | Current Value | Default Value |
|-----------------|------------------------------|------------------------------------|---|---------------|
| Global Settings | Settings / Deployment Macros | Simple_form_example:autoRetry: | String* true  | false |
| Global Settings | Settings / Deployment Macros | Simple_form_example:autoRetryTime: | String* PT60S  | PT60S |

Items 5 1-2 / 2 |< < > >|

Save Cancel



Please note:

- **Save** is only enabled when changes have been made.
- Clicking **Save** triggers a restart, changes in the **Configuration** section are directly applied to the service.

Assigning a Global Variable

Change Configuration

Filter: hold x ☐ Expert Mode Invalid: 3 Edited: 0 / 73

| Category | Section | Key | Current Value | Default Value |
|-----------------|------------------------------|------------------------------|---------------|---------------|
| Global Settings | Settings / Deployment Macros | Simple_form_example.holdTime | String* PT60S | PT60S |


Items: 5 1-1/1 |< >|

[Assign global variable](#) Save Cancel

If you want to use a global variable instead of entering a value manually, click **Assign global variable**




✓ For detailed information about global variables and how to create them, refer to [Managing Global Variables for Containerized xUML Services](#).



A menu opens in which all available global variables are displayed that are of the same type as the current value that you want to change.

Hover over a global variable to display its description in a tooltip.

Use option **Show Global Variables** to open the global variables view. It shows all available global variables and their details. You can also create new global variables here (refer to [Managing Global Variables for Containerized xUML Services](#) for more information).



Click a global variable in the list to apply its value to the **Current Value** field. To emphasize that a global variable is used, a corresponding note is displayed.

**Please note:**

- **S**a**v**e is only enabled when changes have been made.

- Clicking **Save** triggers a restart, changes in the **Configuration** section are directly applied to the service.

Filtering the Settings' List

Change Configuration

Filter

padding

×

☐ Expert Mode

| Section | Key | Current Value |
|------------|---------------|-------------------|
| SAP Global | FieldPadding: | String * NEVER |

As there are many available settings, use the filter field to search for the setting you want to modify.

The content of the filter field is applied to the columns **Section** and **Key**.

Change Configuration

Filter

padding

×

☐ Expert Mode

Section (1)

Reset Filter

Base

REST Service Base

REST Service Base

☐ Settings / Deployment Macros

☐ SAP Global

☐ SOAP HTTP Service Request

☐ SOAP HTTP Server

☒ REST Service Base

☐ SOAP HTTP UI Server

☐ URL Adapter

Click **Extended filter** to display the extended filter options:

- **Section**
- **Reset Filter**

If a filter is applied, the extended filter changes to .

Change Configuration

Filter

Section (1)

Reset Filter

REST Service Base

REST Service Base

REST Service Base

REST Service Base

☐ Settings / Deployment Macros
 ☐ SAP Global
 ☐ SOAP HTTP Service Request
 ☐ SOAP HTTP Server
 ☒ REST Service Base
 ☐ SOAP HTTP UI Server
 ☐ URL Adapter
 ☐ Persistent State
 ☐ Dump Configuration
 ☐ SQL Adapter Connection
 ☐ REST Adapter
 ☐ REST HTTP Server
 ☐ SQL Adapter Authorization
 ☐ WSDL

Reset Selection

In the main filter window, you can reset all selected filters.

Click **Reset Filter**.

In the filter option window, you can also reset the selection.

xUML Service Settings

The settings are categorized into the following:

- **Global Settings:** In this category, you can change setting values that are global to the xUML service. Deployment information retrieved with deployment macros can be overwritten in this category, too (see **Global Settings** below).
- **Add-ons:** In this category, the settings comprise add-on related values like tagged values, interface URIs, and others. For instance, data of the SQL adapter, File System adapter, Timer, or SOAP service request may be overwritten. For more details, refer to the example below in **Add-on Settings**.





You can modify settings of a service no matter if the service is running or if it has been stopped. Saving the changes triggers a re-create and restart of the container. Changing the settings on a stopped service will start the service. Settings will be stored, so if you stop the service and restart it, the settings are restored.

If you delete a service, all settings are lost and cannot be recovered.

Global Settings

| Settings Group | Setting | Description | Allowed Values |
|------------------------------|-------------------|-------------|----------------|
| Settings / Deployment Macros | Service Composite | | |
| | | | |

| | | |
|-----------------------------------|---|------------------|
| getCompositeCategory | Value returned by Action Language macro getCompositeCategory() . Initial value of this setting is the category specified in the service details (see Managing the Service Details). You can change this value here. | any string |
| getCompositeName | Value returned by Action Language macro getCompositeName() . Initial value of this setting is the service name. You can change this value here. | any string |
| getCompositeVersion | Value returned by Action Language macro getCompositeVersion() . Initial value of this setting is the service version in the service details (see Managing the Service Details). You can change this value here. | a version string |
| PAS Platform | | |
| KeycloakInstance::clientId | Specify the clientId to use when authenticating the service. Default is keycloak-clientId . <div> The clientId is defined in Keycloak, it should be changed in production to define specific authorization for this service.</div> | any string |
| KeycloakInstance::clientSecret | Specify the clientSecret associated to the clientId. Default is keycloak-clientSecret . <div> The clientSecret is defined in Keycloak, it should be changed in production to define specific authorization for this service.</div> | any string |
| KeycloakAlias::Location: host | Specify the hostname (domain) of the Keycloak SSO system. Default is keycloak-host . | any string |
| KeycloakAlias::Location: basePath | Specify the subpath of the Keycloak system. Default is keycloak-basePath . | any string |
| KeycloakAlias::Location: port | Specify the port of the Keycloak system. Default cannot be changed. | 8080 |
| KeycloakAlias::Location: protocol | Specify the protocol of the Keycloak system. Default cannot be changed. | http |
| Service | | |
| <service settings> | In your Designer service, you can define name-value pairs using the setting macro in an implementation. These values can be modified here. | |

Add-on Settings


Each xUML service adapter has its own settings that are initialized in the xUML model and can be changed in the configuration.

If you are running an xUML service that is connecting to a database backend, you can modify the tagged values of the database interface respectively dependency. Before starting a deployed xUML service that connects to a database backend, you may want to redefine required database parameters.

Generally, most of the add-on settings that are related to an xUML Service Adapter have a corresponding tagged value in the component diagram. Refer to the [documentation of the corresponding adapter](#) for these settings.

SQL Adapter Connection Settings

| Key | Value |
|---------------|--|
| DBType | Name of the SQL Service component, e.g. SQLite |
| DBName | Name of the database, e.g. ScheerACME_Customers |

| | |
|---------------------------------|---|
| Connection Pooling | This tagged value controls the connection pooling. If true, each connection is put into a pool after use. If an SQL adapter requires a connection, it is taken from the pool. If no connection is available, a new connection is being created and put into the pool after use. The time the connection is kept in the pool depends on the other pooling parameters. |
| Max Connection Reuse | <p>This tagged value controls how often a connection can be re-used. After the connection has been re-used for maxConnectionReuse, it will be closed and not put back into the pool. This feature has been introduced because some databases had problems if the connection was re-used too often. Value -1 means the connection will be re-used forever. In this case you should define reasonable values for maxConnectionAge or maxConnectionIdleTime (see above).</p> <div>  Note that the pooling is implicitly switched off, if maxConnectionReuse is set to 0. </div> |
| Max Connection Age | After a given connection age (in minutes) the connection will be closed and removed from the pool. |
| Max Connection Idle Time | Connections not used for the time specified (in minutes) will be closed and removed from the pool. This is useful for connections going through firewalls because such connections might be cut off after some time. |

For more information on the SQL adapter settings (other tagged values, default values, ...) refer to the [xUML Services Reference Guide](#).




SQL Adapter Authorization Settings


These settings allow you to adapt the SQL database user and password of the xUML service.

| Key | Value |
|------------------------------|-------------------|
| customers: DBUser | Database user |
| customers: DBPassword | Database password |

Other Add-on Settings

Find below a list of other add-on settings and their description. For the sake of completeness, we also mentioned settings coming from the model for some setting groups (see column **Specified in Model on**).

| Settings Group | Setting | Specified in Model on | Description | Allowed Values |
|--------------------|-----------------------------|-----------------------|--|---|
| Dump Configuration | Caught Error Code | | <p>Only dump errors with the specified code. Specify a Bridge user defined error code.</p> <div>  This setting takes no effect if Dump not Caught Errors/Dump Context on Error is disabled. </div> | a string |
| | Caught Error Domain | | <p>Only dump errors of the specified error domain. Specify a Bridge user defined error domain.</p> <div>  This setting takes no effect if Dump not Caught Errors/Dump Context on Error is disabled. </div> | a string |
| | Dump Caught Errors: enabled | | <p>Enable/Disable writing an error dump file for errors that have been caught in the xUML service model.</p> <div>  </div> | <div> true <div>Create a service dump for caught errors.</div> </div> |

| | | | | | |
|---------------------------------|---|--------------|---|-------|--|
| | | | <div> This setting takes no effect if Dump not Caught Errors/Dump Context on Error is disabled. </div> | false | Disable service dump for caught errors (default). |
| | Dump not Caught Errors: enabled | | Enable/Disable writing an error dump file at all. This setting corresponds to the xUML service preference Dump Context on Error (refer to Integration Platform User's Guide > Preferences of an xUML Service). | true | Create a service dump for not caught errors (default). |
| | | | | false | Disable service dump for not caught errors. This disables error dump at all. |
| Persistent State | Owner | | <p>Change the name of the persistent state object owner here. Each persistent state object is owned by a persistent state engine. If you change the owner setting, all subsequently created persistent state objects will belong to the new owner.</p> <div>  All existing persistent state objects of the old owner will not be processed anymore by this service as they belong to a different owner now. </div> | | |
| | Worker Limit | Composite | <p>Specify the worker limit.</p> <p>Workers defines the maximum number of parallel threads used to process pending events. The default setting is 5, which is used if none or 0 workers are configured. The implications of more or less workers are discussed in xUML Service Reference Guide > Performance Considerations of Persistent State.</p> | | |
| REST Service HTTP Server | Descriptor : Cache Control: value | | <p>Specify the Browser caching options for the YAML file by setting a value for HTTP header <code>Cache-Control</code>. For more information on this header, refer to Cache-Control on the Mozilla pages.</p> | | |
| | Test Tool: Cache Control: value | | <p>Specify the Browser caching options for the Swagger UI by setting a value for HTTP header <code>Cache-Control</code>. For more information on this header, refer to Cache-Control on the Mozilla pages.</p> | | |
| REST Service Base | <your service name>: enabled | | <p>Switch the service port on / off. When the service port is deactivated, it will not accept any request anymore.</p> | true | Service port is active (default). |
| | | | | false | Service port is deactivated. |
| | <your service name>: JSONComposerOptions: compact | REST Service | <p>Specify the JSON compose option for the REST request/response.</p> <p>When jsonCompact is true, the JSON composer will generate compact JSON, otherwise it will generate pretty JSON. jsonCompact defaults to true - also on re-compile of an older model with Builder as of 7.0.0-beta3.</p> | true | Generate compact JSON (default). |
| | | | | false | Generate pretty JSON. |
| | <your service name>: JSONComposerOptions: keepNulls | REST Service | <p>Specify the JSON compose option for the REST request/response.</p> <p>When jsonKeepNulls is true, attributes of the REST response object having NULL values will be rendered to the REST response, otherwise they will be left out completely (refer to xUML Service Reference Guide > NULL Values).</p> | true | Render attributes with NULL values to the REST call. |

| | | | | | |
|---------------------------------|--|--|--|--------------|---|
| | | | | false | Leave out attributes with NULL values in the REST call (default). |
| | <your service name>: Maximum Connections: | | Change the maximum number of parallel requests to the service port. | | |
| | <your service name>: Port | | Change the port the xUML service listens to. The original value comes from the SOAP service component. | | a valid port number |
| | <your service name>: ResolveHostnames | | Define whether the host name is logged to the service logs instead of the IP address. | true | Resolve the IP address to the hostname in the service logs (default). |
| | | | | false | Write the IP address to the service logs. |
| SOAP HTTP Server | Allow Tracing | | Switching tracing on / off. All xUML services are compiled with tracing enabled. This option allows you to turn off the tracing, so that no trace information is returned by the Bridge when a service is called. | true | The Runtime returns tracing information on request (default). |
| | | | | false | The Runtime does not return tracing information. |
| | Maximum Connections | | Change the maximum number of parallel requests to the service port. | | |
| | ResolveHostnames | | Define whether the host name is logged to the service logs instead of the IP address. | true | Resolve the IP address to the hostname in the service logs (default). |
| | | | | false | Write the IP address to the service logs. |
| | <your service name>Port | | Change the port the xUML service listens to. The original value comes from the SOAP service component. | | a valid port number |
| SOAP HTTP Server Request | <your service name>: <your port type>: enabled | | Switch the service port on / off. When the service port is deactivated, it will not accept any request anymore. | true | Service port is active (default). |
| | | | | false | Service port is deactivated. |

| | | | | | |
|--|--|-----------------------------------|--|-------------------------------|--|
| | <your service name>: <your port type>: URI | Component diagram | Change the service URI. The default value comes from the component diagram of the xUML service. | | |
| SOAP HTTP UI Server | Library Cache Control: value | | Specify the Browser caching options for the UI files (HTML, CSS, ...) by setting a value for HTTP header <code>Cache-Control</code> . For more information on this header, refer to Cache-Control on the Mozilla pages. | | |
| WSDL: <your service name> | WSDL: <your service name> host | | Specify the host name of the server for the xUML service WSDL. | <code>server_hostname</code> | Name of the Bridge node instance the service is deployed to. |
| | | | | a fully qualified system name | |

Expert Mode

Use the checkbox **Expert Mode** to display further options:

Change Configuration

Filter ☐ ☒ **Expert Mode** Edited 0 / 77

| Category | Section | Key | Name | Current Value | Default Value |
|-----------------|------------------------------|--------------------------|----------------------------|-----------------|---------------|
| Global Settings | Settings / Deployment Macros | Ticketcreation.holdTime | G_TICKETCREATION_HOLDTIME | String PT60S | PT60S |
| Global Settings | Settings / Deployment Macros | Ticketcreation.autoretry | G_TICKETCREATION_AUTORETRY | String false | false |
| Global Settings | Settings / Deployment Macros | AuthenticationEnabled | G_AUTHENTICATORENABLED | String true | true |

If you want to set xUML service settings for containerized services from the outside using the xuml-tool, you will need the **Name** (= *friendly Id*) as the environment variable. Refer to [Integration Platform User's Guide > xUML Runtime Tool](#) for details.