








Adapting the Configuration of Containerized xUML Services


 This option is only available for type **xuml-service** (= containerized xUML services).

The administration application allows you to change the configuration of a containerized xUML service.

Name	Type	Quick Actions
 ticketsystem	xuml-service	     
 ideamanagement	xuml-service	     

The administration application allows you to change the configuration of a Docker container.

You have two options to open the configuration of a container:

- Click **Edit configuration** on  in the quick actions bar in the services' list.

- Open the details page of the service and scroll down to section **Configuration**.

On this Page:

- [xUML Service Settings](#)
 - [Settings / Deployment Macros](#)
 - [Adapter Settings](#)
 - [Other](#)
- [Expert Mode](#)

Related Pages:

- [Working With the Administration](#)
 - [Working With the Deployment Wizard](#)
- [Controlling Containerized xUML Services](#)
 - [Changing the Log Level of a Containerized xUML Service](#)
 - [Persistent States of Containerized xUML Services](#)
 - [Showing Logs of a Containerized xUML Service](#)
- [Controlling Docker Container](#)

Related Documentation:

- [Designer](#)
 - [Managing the Service Details](#)
- [BRIDGE Integration Platform User's Guide](#)

Details of ticketsystem

 **running**   

Information


Details

Documentation

Logs

History Log

Persistent State

Configuration 

Change Configuration

Filter ☒ Expert Mode ⚠ Invalid 4 Edited 0 / 77

Section	Key	Current Value	Default Value
Settings / Deployment Macros	Ticketcreation:holdTime:	String PT60S	PT60S
Settings / Deployment Macros	Ticketcreation:autoRetry:	String false	false
Settings / Deployment Macros	-AuthenticatorEnabled:	String true	true
SAP Global	DefaultConnectionPoolSize:	String 10	10
SOAP HTTP Service Request	BPAN_RESTService:TicketcreationRest.UR:	String /rest/process/Ticketcreation	/rest/process/Ticketcreation

Items 5 1-5 / 77 |< < > >|

In the **Configura**
tion section you
can directly
modify xUML
service settings.
When you save
your changes,
the container will
be re-created
and restarted.
Changes are
possible after
the first
deployment of
the
containerized
service.

Change Configuration

Filter ☒ Expert Mode ⚠ Invalid 4 Edited 1 / 77

Section	Key	Current Value	Default Value
Settings / Deployment Macros	Ticketcreation:autoRetry:	String true	false
Settings / Deployment Macros	Ticketcreation:autoRetryTime:	String PT60S	PT60S

Items 5 1-2 / 2 |< < > >|

You can change
the **Current**
Value of a
service setting.

The **Default**
Value is
displayed next
to the current
value.
If you want
to reset the setting
to its default,

click **Reset** .

Click **Save** after
you have
completed your
changed.

 **Please
note:**

- **S**a**v**e is only enabled when changes have been made.

- Clicking **Save** triggers a restart, changes in the **Configuration** section are directly applied to the service.

Change Configuration

Filter

Invalid 4

Edited: 1 / 77

Section

Key

Current Value

Default Value

Settings / Deployment Macros

Ticketcreation:holdTime:

String *
PT60S

PT60S

Settings / Deployment Macros

Ticketcreation:autoRetry:

String *
true

false

Settings / Deployment Macros

..AuthenticatorEnabled:

String *
true

true

SAP Global

DefaultConnectionPoolSize:

String *
10

10

SOAP HTTP Service Request

Invalid

BPMN_RESTService: TicketcreationRest-URI:

String
/rest/process/Ticketcreation

/rest/process /Ticketcreation

Items 5

1 - 5 / 77


<

>

Save

Cancel

Service settings can be erroneous if a setting name contains special characters or whitespaces. Invalid service settings are

marked . Their number is also displayed on top right of the list.

If a service setting is erroneous, you cannot change its current value.

In case that your service contains erroneous settings, you can do the following:

- If it is a setting in a Designer service ("custom value"): Open the service in the [Designer](#), correct the settings' name and redeploy the service.
- If it is a setting in a platform service, please contact our [support team](#).

Change Configuration

Filter

padding

Expert Mode

Section

Key

Current Value




SAP Global

FieldPadding:

String *
NEVER

As there are many available settings, use the filter field to search for the setting you want to modify.

The content of the filter field is applied to the columns **Section** and **Key**.

	<p>Click Extended filter to display the extended filter options:</p> <ul style="list-style-type: none"> • Section • Reset Filter <p>If a filter is applied, the extended filter changes to .</p>
	<p>In the main filter window, you can reset all selected filters. Click Reset Filter.</p> <p>In the filter option window, you can also reset the selection.</p>






xUML Service Settings



You can modify settings of a service no matter if the service is running or if it has been stopped. Saving the changes triggers a re-create and restart of the container. Changing the settings on a stopped service will start the service. Settings will be stored, so if you stop the service and restart it, the settings are restored.

If you delete a service, all settings are lost and cannot be recovered.

Settings / Deployment Macros

Setting	Description	Allowed Values	
Service Composite			
getCompositeCategory	Value returned by Action Language macro getCompositeCategory() . Initial value of this setting is the category specified in the service details (see Managing the Service Details). You can change this value here.	any string	
getCompositeName	Value returned by Action Language macro getCompositeName() . Initial value of this setting is the service name. You can change this value here.	any string	
getCompositeVersion	Value returned by Action Language macro getCompositeVersion() . Initial value of this setting is the service version in the service details (see Managing the Service Details). You can change this value here.	a version string	
PAS Platform			
AuthenticatorEnabled	<div>Specify whether users are allowed to identify themselves using an x-pas-user header instead of a bearer token.</div> <div><div> For compatibility reasons true (x-pas-header allowed) is the default option but this is deprecated and may lead to security issues. If you do not rely on the x-pas-header, we recommend setting this option to false.</div></div>	<div>true</div> <div>Allow using an x-pas-header or a bearer token for authentication (default).</div> <div>false</div> <div>Authentication only by bearer token.</div>	
AuthService::minimalAccessTokenLifeSpan	<div>Define when a refresh token should be triggered. Default is 30 (if the token last less than 30 seconds it will be refreshed before it is used).</div> <div><div> In general there is no need to change the default of 30 seconds.</div></div>	any integer	
KeycloakInstance::clientId	<div>Specify the clientId to use when authenticating the service. Default is keycloak-clientId.</div> <div><div> The clientId is defined in Keycloak, it should be changed in production to define specific authorization for this service.</div></div>	any string	
KeycloakInstance::clientSecret	<div>Specify the clientSecret associated to the clientId. Default is keycloak-clientSecret.</div> <div><div> The clientSecret is defined in Keycloak, it should be changed in production to define specific authorization for this service.</div></div>	any string	
KeycloakAlias:Location:host	Specify the hostname (domain) of the Keycloak SSO system. Default is keycloak-host .	any string	
KeycloakAlias:Location:basePath	Specify the subpath of the Keycloak system. Default is keycloak-basePath .	any string	
KeycloakAlias:Location:port	Specify the port of the Keycloak system. Default cannot be changed.	8080	
KeycloakAlias:Location:protocol	Specify the protocol of the Keycloak system. Default cannot be changed.	http	
PasSecurityService::allowAnonymous	<div>Specify whether anonymous users (no PAS users) should be allowed to send requests to the PAS BPMN service. In contrast to anonymous users, PAS users are identified by a bearer token or x-pas-user header).</div> <div>If this setting is set to false, requests of unauthenticated users will return HTTP error 401.</div> <div><div> This setting does not disable any role configuration within the BPMN. If there are lanes configured in the BPMN, the service can only be accessed by authenticated users.</div></div>	<div>true</div> <div>Allow anonymous access (default).</div>	

		false	Access for identified users only.
Service			
<service settings>	In your Designer service, you can define name-value pairs using the setting macro in an implementation. These values can be modified here.		

Adapter Settings




Each xUML service adapter has its own settings that are initialized in the xUML model and can be changed in the configuration.


If you are running an xUML service that is connecting to a database backend, you can modify the tagged values of the database interface respectively dependency. Before starting a deployed xUML service that connects to a database backend, you may want to redefine required database parameters.

Generally, most of the add-on settings that are related to an xUML Service Adapter have a corresponding tagged value in the component diagram. Refer to the [documentation of the corresponding adapter](#) for these settings.

Other

Find below a list of other add-on settings and their description. For the sake of completeness, we also mentioned settings coming from the model for some setting groups (see column **Specified in Model on**).

Settings Group	Setting	Specified in Model on	Description	Allowed Values	
Dump Configuration	Caught Error Code		Only dump errors with the specified code. Specify a Bridge user defined error code.  This setting takes no effect if Dump not Caught Errors/Dump Context on Error is disabled.	a string	
	Caught Error Domain		Only dump errors of the specified error domain. Specify a Bridge user defined error domain.  This setting takes no effect if Dump not Caught Errors/Dump Context on Error is disabled.	a string	
	Dump Caught Errors: enabled		Enable/Disable writing an error dump file for errors that have been caught in the xUML service model.  This setting takes no effect if Dump not Caught Errors/Dump Context on Error is disabled.	true	Create a service dump for caught errors.
				false	Disable service dump for caught errors (default).
	Dump not Caught Errors: enabled		Enable/Disable writing an error dump file at all. This setting corresponds to the xUML service preference Dump Context on Error (refer to Integration Platform User's Guide > Preferences of an xUML Service).	true	Create a service dump for not caught errors (default).
				false	Disable service dump for not caught errors. This disables error dump at all.

Persistent State	Owner		Change the name of the persistent state object owner here. Each persistent state object is owned by a persistent state engine. If you change the owner setting, all subsequently created persistent state objects will belong to the new owner.		
			 All existing persistent state objects of the old owner will not be processed anymore by this service as they belong to a different owner now.		
	Worker Limit	Composite	Specify the worker limit. Workers defines the maximum number of parallel threads used to process pending events. The default setting is 5, which is used if none or 0 workers are configured. The implications of more or less workers are discussed in xUML Service Reference Guide > Performance Considerations of Persistent State .		
REST Service HTTP Server	Descriptor : Cache Control: value		Specify the Browser caching options for the YAML file by setting a value for HTTP header <code>Cache-Control</code> . For more information on this header, refer to Cache-Control on the Mozilla pages.		
	Test Tool: Cache Control: value		Specify the Browser caching options for the Swagger UI by setting a value for HTTP header <code>Cache-Control</code> . For more information on this header, refer to Cache-Control on the Mozilla pages.		
REST Service Base	<your service name>: enabled		Switch the service port on / off. When the service port is deactivated, it will not accept any request anymore.	true	Service port is active (default).
				false	Service port is deactivated.
	<your service name>: JSONComposerOptions: compact	REST Service	Specify the JSON compose option for the REST request/response. When jsonCompact is true, the JSON composer will generate compact JSON, otherwise it will generate pretty JSON. jsonCompact defaults to true - also on re-compile of an older model with Builder as of 7.0.0-beta3.	true	Generate compact JSON (default).
				false	Generate pretty JSON.
	<your service name>: JSONComposerOptions: keepNulls	REST Service	Specify the JSON compose option for the REST request/response. When jsonKeepNulls is true, attributes of the REST response object having NULL values will be rendered to the REST response, otherwise they will be left out completely (refer to xUML Service Reference Guide > NULL Values).	true	Render attributes with NULL values to the REST call.
				false	Leave out attributes with NULL values in the REST call (default).
	<your service name>: MaximumConnections:		Change the maximum number of parallel requests to the service port.		
	<your service name>: Port		Change the port the xUML service listens to. The original value comes from the SOAP service component.	a valid port number	

	<your service name>: ResolveHostnames		Define whether the host name is logged to the service logs instead of the IP address.	true	Resolve the IP address to the hostname in the service logs (default).
				false	Write the IP address to the service logs.
SOAP HTTP Server	Allow Tracing		Switching tracing on / off. All xUML services are compiled with tracing enabled. This option allows you to turn off the tracing, so that no trace information is returned by the Bridge when a service is called.	true	The Runtime returns tracing information on request (default).
				false	The Runtime does not return tracing information.
	Maximum Connections		Change the maximum number of parallel requests to the service port.		
	ResolveHostnames		Define whether the host name is logged to the service logs instead of the IP address.	true	Resolve the IP address to the hostname in the service logs (default).
				false	Write the IP address to the service logs.
	<your service name>Port		Change the port the xUML service listens to. The original value comes from the SOAP service component.	a valid port number	
SOAP HTTP Server Request	<your service name>: <your port type>: enabled		Switch the service port on / off. When the service port is deactivated, it will not accept any request anymore.	true	Service port is active (default).
				false	Service port is deactivated.
	<your service name>: <your port type>: URI	Component diagram	Change the service URI. The default value comes from the component diagram of the xUML service.		
SOAP HTTP UI Server	Library Cache Control: value		Specify the Browser caching options for the UI files (HTML, CSS, ...) by setting a value for HTTP header <code>Cache-Control</code> . For more information on this header, refer to Cache-Control on the Mozilla pages.		

WSDL: <your service name>	WSDL: <your service name> host		Specify the host name of the server for the xUML service WSDL.	<div> \$ { se rv er _h os tn am e} </div>	Name of the Bridge node instance the service is deployed to.
				a full y qu alif ied sy ste m na me	

Expert Mode

Use the checkbox **Expert Mode** to display further options:

Change Configuration

Filter

Expert Mode

RAM

256 MB

Invalid 4 Edited 0 / 77

Section	Key	Name	Current Value	Default Value
Settings / Deployment Macros	Ticketcreation:holdTime	G_TICKETCREATION_HOLDTIME	PT50S	PT60S
Settings / Deployment Macros	Ticketcreation:autoRetry	G_TICKETCREATION_AUTORETRY	false	false
Settings / Deployment Macros	AuthenticationEnabled	G_AUTHENTICATORENABLED	true	true

Option	Description
RAM	Use the slider to increase or decrease the RAM of a service. This option allows you to avoid that one service can consume all resources. Default is 256 MB, the RAM maximum is 4 GB. You can change the RAM in steps of 64 MB.
Name	If you want to set xUML service settings for containerized services from the outside using the xuml-tool, you will need the Name (= <i>friendly Id</i>) as the environment variable. Refer to Integration Platform User's Guide > xUML Runtime Tool for details.