

Modifying a User

Users who are member of a group, to which the role **MODELER** or **USER** has been assigned, may only modify their own user password.

Users

Id	Name	Group	Role	Active	Actions
admin	ACME Admin	admin	ADMIN	yes	<div>ModifyDelete</div>
david.stringer	David Stringer	developer	MODELER	yes	<div>ModifyDelete</div>
holden.caulfield	Holden Caulfield	production	USER	yes	<div>ModifyDelete</div>
jane.marple	Jane Marple	admin	ADMIN	yes	<div>ModifyDelete</div>
john.watson	John Watson	production	USER	yes	<div>ModifyDelete</div>
technical_user	Technical user for automated tasks (do not use to log in manually)	automation	USER	yes	<div>ModifyDelete</div>

Create New User

Click **Modify** on the user you want to modify.

The dialog for modifying users is displayed:

Modify User

User Id

holden.caulfield

User Name

Holden Caulfield

Active

☒

Group ID

production

Password

Retype Password

Apply

Cancel

User Id	The user id is needed to login to the Bridge and must be unique in the domain. Letters, numeric characters, and the following special characters are allowed: , : . _ / () = ? } [] @ # ! > -
User Name	Letters, numeric characters, space character, and the following special characters are allowed: , : . _ / () = ? } [] @ # ! > -
Active	You need to activate the user by selecting the checkbox Active . Only active users can login to the Bridge.

Group Id	The dropdown menu provides all group ids existing in the domain. Depending on your choice, the user will have full or restricted access to the functions of the Bridge (see Group Roles).
Password	<p>The user will need a password to login to the Bridge. The maximal password length is 50 characters.</p> <p>Make sure that the password ...</p> <ul style="list-style-type: none"> • is 8 to 42 characters long. • starts with a character. • is alphanumeric. • contains at least one number. • contains only the allowed special characters (!, @, #, \$, %).
Retype Password	Retype the password to ensure correct spelling.

Click **Apply** to save your changes. The changed user details will be replicated to each node instance of the domain.

Canceling the modification will bring you back to the user list.

After having modified the user, the user list will be displayed again.

You cannot change the group assignment of the pre-defined administration user (**admin**), and you cannot deactivate this user.