

Summary of User Access Rights

Find below a table summarizing the user access rights of the E2E Bridge. The functions are sorted according to the navigation items in the Bridge.

You can change the default user access rights by editing file **roles.xml** as described on [Modifying User Access Rights](#).

Function/Role	Permission from roles.xml	Default Permissions		
		ADMIN	MODELER	USER
General				
General Bridge Access	common/welcome common/logout common/domain common/nodes	✔	✔	✔
Bridge API documentation	bridgeinst/documentation	✔	✔	✔
Users				
View user list	domain/users	✔	✔	✔
View user	domain/user_modify	✔	only own user	only own user
Manage user	domain/user_create domain/user_modify_name domain/user_modify_group domain/user_modify_active domain/user_delete	✔	✘	✘
Change user password	domain/user_modify_passwd	✔	only of own user	only of own user
Groups				
View group list	domain/groups	✔	✘	✘
Manage group	domain/group_create domain/group_modify domain/group_modify_name domain/group_modify_role domain/group_delete	✔	✘	✘
Node Instances				
View domain E2E Bridge instance list	domain/nodes	✔	✘	✘
Manage domain	domain/node_import domain/node_remove	✔	✘	✘
Convert to stand-alone	domain/node_convert	✔	✘	✘
<node instance name>				
View Bridge preferences	console/prefs	✔	✔	✔
Modify Bridge preferences	console/prefs_modify console/prefs_modify_logging console/prefs_modify_trace console/prefs_modify_display_name console/prefs_modify_monitoring_url	✔	✘	✘
View Bridge logging	console/logging	✔	✔	✔
View firmware information	console/firmware	✔	✔	✔
Manage firmware	console/firmware_modify	✔	✘	✘
Deployment				
Deploy new	deploy/create	✔	✔	✘
Deploy and overwrite	deploy/replace	✔	only if deployed by member of same group	✘
Proxy Services				

On this Page:

- [Users](#)
- [Groups](#)
- [Node Instances](#)
- [<node instance name>](#)
- [Deployment](#)
- [Proxy Services](#)
- [xUML Services](#)
- [<xUML service>](#)
- [<node.js service>](#)
- [<Java service>](#)

Related Pages:

- [Modifying User Access Rights](#)

Create proxy node	proxynode/create	✓	✗	✗
Delete proxy node	proxynode/delete	✓	✗	✗
Stop proxy services	proxyserver/start	✓	✗	✗
Stop proxy services	proxyserver/stop	✓	✗	✗
View proxy services logging	proxyserver/logging	✓	✓	✓
View proxy configuration files and templates	proxyserver/prefs	✓	✓	✓
Edit proxy configuration files and templates	proxyserver/prefs_modify proxyserver/prefs_modify_admin	✓	✗	✗
View proxy entries	proxynode/entries	✓	✓	✓
View certificate	proxynode/certs	✓	✓	✓
Manage certificate	proxynode/certs_modify	✓	✗	✗
xUML Services				
View service list	bridgeserver/instances	✓	✓	✓
View ports		✓	✓	✓
View preferences	bridgeserver/plugins	✓	✓	✓
Edit preferences	bridgeserver/ plugins_modify	✓	✗	✗
View licensing information	bridgeserver/licensing	✓	✓	✓
Manage licenses	bridgeserver/licensing_mo dify	✓	✗	✗
Deploy/Manage resources	bridgeserver/resource bridgeserver/resource_mod ify	✓	✗	✗
Deploy/Manage Java archives	bridgeserver/java bridgeserver/java_modify	✓	✗	✗
Deploy/Manage XSLT script archives	bridgeserver/xslt bridgeserver/xslt_modify	✓	✗	✗
View setting variables	bridgeserver/variables	✓	✓	✗
Modify setting variables	bridgeserver/ variables_modify	✓	✗	✗
<xUML service>				
View status	bridgeinst/status	✓	✓	✓
Start/Stop	bridgeinst/start bridgeinst/stop	✓	only if deployed by member of same group	✗
Kill	bridgeinst/kill	✓	✗	✗
Export service	bridgeinst/export	✓	only if deployed by member of same group	✗
Delete	bridgeserver/ delete_instance	✓	only if deployed by member of same group	✗
View preferences	bridgeinst/prefs	✓	✓	✓
Modify preferences	bridgeinst/prefs_modify bridgeinst/prefs_modify_s tartup bridgeinst/prefs_modify_a utomatic_restart bridgeinst/prefs_modify_o wner bridgeinst/prefs_modify_l ogging bridgeinst/prefs_modify_t ransaction_logging	✓	all preferences but automatic startup and owner if deployed by member of same group	✗
View history	bridgeinst/history	✓	✓	✓
View logging	bridgeinst/logging	✓	✓	✓
View error dump	bridgeinst/dump	✓	✓	✓

Delete error dump	bridgeinst/dump_modify	✓	✓	✗
Trace with E2E Analyzer		✓	only if deployed by member of same group	✗
View/Modify/Export settings	bridgeinst/templates bridgeinst/templates_modify	✓	only if deployed by member of same group	✗
View version	bridgeinst/documentation	✓	✓	✓
View persistent state information	bridgeinst/state_classes bridgeinst/state_objects bridgeinst/state_object bridgeinst/state_events	✓	✓	✓
Manage persistent state objects	bridgeinst /state_classes_modify bridgeinst /state_objects_modify bridgeinst /state_object_modify bridgeinst /state_events_modify	✓	only if deployed by member of same group	✗
Delete all persistent state objects	bridgeinst/state_delete	✓	✗	✗
<node.js service>				
View status	nodejs/modify	✓	✓	✓
Start/Stop	nodejs/modify	✓	only if deployed by member of same group	✗
Delete	nodejs/modify	✓	only if deployed by member of same group	✗
View preferences	nodejs/modify	✓	✓	✓
Modify preferences	nodejs/modify	✓	if member of same group deployed it: all preferences but automatic startup and owner	✗
View history	nodejs/modify	✓	✓	✓
View logging	nodejs/modify	✓	✓	✓
View/Modify environment variables	nodejs/modify	✓	only if deployed by member of same group	✗
<Java service>				
View status	java/modify	✓	✓	✓
Start/Stop	java/modify	✓	only if deployed by member of same group	✗
Delete	java/modify	✓	only if deployed by member of same group	✗
View preferences	java/modify	✓	✓	✓
Modify preferences	java/modify	✓	if deployed by member of same group: all preferences but automatic startup and owner	✗
View history	java/modify	✓	✓	✓
View logging	java/modify	✓	✓	✓
View/Modify environment variables	java/modify	✓	only if deployed by member of same group	✗