
Logger Adapter

With the Log Adapter you can write log messages to the standard or transaction log of an xUML service. To write these log messages, you can use

- the Log adapter, see
 - Writing into the Standard xUML Service Log
 - Writing into the xUML Service Transaction Log
- action script (see the log() Function and report() Function functions)

The logging follows the channel and sinks concepts.



For more information on the logger concept, refer to xUML Runtime Logger Configuration.

Adding a Logger Adapter Operation to a Diagram



Expand the path to the Logger adapter in the service panel (Ba se Types /Bridge Base /Base Compon ents /Add Ons /Logger).

On this Page:


- Adding a Logger Adapter Operation to a Diagram
- Configuring a Logger Adapter Operation

Related Pages:

- Writing into the Standard xUML Service Log
- Writing into the xUML
 Consider Transportion Lea
- Service Transaction Log
- Logger Adapter Reference
- log() Function
- report() Function
- Contents of the Transaction Log


Related Documentation:

- xUML Service Standard Log
- xUML Service Transaction
 Log
- xUML Runtime Logger Configuration



Configuring a Logger Adapter Operation


Once a Logger operation has been added to a diagram, it needs to be configured as a Logger adapter.




Select the newly added Logger adapter operation and switch to the **Attributes** panel. Depending on the diagram type you can see the following information (example BPMN execution diagram):

Attribute	Description	Allowed Values / Example
Name	The name of the Logger adapter operation.	log
Symbol Type	Operations added to a execution diagram are execution steps.	Execution Step

All this is predefined and cannot be changed.



Click **Add Stereotype** to define the selected operation as to be a Logger adapter.




Select **Logger** from the list of available adapter stereotypes. Click **Save**.




The **Attributes** panel shows the added adapter stereotype. Now you still need to configure the adapter.

Expand the stereotype by clicking the arrow on the right.



To configure the Logger adapter, you have the following options:

- action: For the logger adapter you have to configure an adapter action. For more information see below.
- channel: This option is not enabled yet, but will be available to you soon.



Click the text **Select an option** or the arrow on the right and select the name of the respective operation as action from the dropdown list.



If the action is not set, the Logger adapter always defaults to **log**.

Refer to Logger Adapter Reference for detailed information.